

# **U-WAVEPAK-BW**

## **Setup Manual**

Read this Setup Manual thoroughly before using the application.

After reading, retain it close at hand for future reference.

**Mitutoyo**

**Notice: Please make sure to confirm the following before installation**

This program is created and distributed for free by Mitutoyo as part of its customer service.

Whether explicitly or implicitly, Mitutoyo cannot guarantee the quality and performance of this program.

Mitutoyo cannot accept liability for any damage arising from the use of this program (including damage, failure, other consequential damage, etc. of hardware, other programs and data), either directly or indirectly.

-Mitutoyo shall not be responsible for any result and related influence caused by the operation of this program and manual.

-All copyright for this program and manual belongs to Mitutoyo.

-No one shall be allowed to revise part or all of this program without permission.

-If this program is copied, reproduced or assigned to a third party, the entire material including this manual must be included in complete condition. Elimination or revision of this manual, and the copying, reproduction or assignment of part of this program is strictly prohibited.

**Notice: About U-WAVE-TCB/U-WAVE-TMB and U-WAVEPAK-BW**

-This application operates on Windows10. Please ensure to run it on a PC with Windows10 installed.

-This application can use the Bluetooth function that comes with the device. The terminal without Bluetooth function purchases commercial Bluetooth receiver, and please use it.

-This application and U-WAVE-TCB/U-WAVE-TMB do not guarantee the connection with all Bluetooth apparatuses.

※ This application has been confirmed to work with windows10 Pro.

## Table of Contents

1.	Installation .....	2
2.	Setting up the U-WAVE-TCB/U-WAVE-TMB .....	2
2.1.	How to connect the U-WAVE-TCB/U-WAVE-TMB to the U-WAVEPAK-BW .....	2
2.2.	How to disconnect the U-WAVE-TCB/U-WAVE-TMB from the U-WAVEPAK-BW.....	9
3.	Inputting measurement values.....	10
4.	Measurement modes.....	11
5.	Editing the settings.....	12
5.1.	Modifying the settings.....	12
5.2.	Deleting the settings.....	15
6.	Setting the connection to a higher-level application software (MeasurLink, ITPAK, etc.) .....	19
7.	How to uninstall U-WAVEPAK BW .....	20

## 1. Installation

- (1) Double-click on [uwavepakble\_setup.exe]
- (2) Complete the installation following the installation guidance displayed on the window.


## 2. Setting up the U-WAVE-TCB/U-WAVE-TMB

### 2.1. How to connect the U-WAVE-TCB/U-WAVE-TMB to the U-WAVEPAK-BW

- (1) Double-click on [U-WAVEPAK-BW] to run the application, U-WAVEPAK-BW.




The following window will be displayed, signaling the completion of the starting up of the application.





- (2) The maximum number of units of U-WAVE-TCB/U-WAVE-TMB to be set up is seven.

To set up a U-WAVE-TCB/U-WAVE-TMB, click on a number in the table [U-WAVE Information].


You can also select a number from the drop-down list at the top-right of the window.



(3) Click on the [U-WAVE Setting] button to open the setting window.




- (4) Press the “Data” button (orange button) attached to the connection unit of the U-WAVE-TCB/U-WAVE-TMB. The LED of the U-WAVE-TCB/U-WAVE-TMB will flash in orange. After the U-WAVE-TCB/U-WAVE-TMB has been detected by the U-WAVEPAK-BW, its ID number will be displayed in the item [Detected U-WAVE].




#### Tips:

- The detected ID number can be found on the label stuck on the body of a U-WAVE-TCB/U-WAVE-TMB.
- If the U-WAVE-TCB/U-WAVE-TMB cannot be detected, press the “DATA” button again. There will be cases where it cannot be detected depending on the timing at which you press the button. If it is not still detected, turn off the Bluetooth communication of the OS, turn on the Bluetooth communication again, and try detection.
- When the [U-WAVE Setting] window is open, the red LED of the U-WAVE-TCB/U-WAVE-TMB will either start flashing, or its buzzer will start beeping, regardless of whether the connection is successful or not.
- If a U-WAVE-TCB/U-WAVE-TMB has already been set up, its ID number will not be detected.
- If the U-WAVE-TCB/U-WAVE-TMB is connected to applications other than this application, its ID number will not be detected.

(5) Click on the detected ID number, and then click the [Device decision] button.



(6) Confirm that the ID number has shown up in the item [Device ID] at the right of the window, and then click on the [Confirm] button.




#### Tips:

- A device name can be changed voluntarily.
- Any message can be stored in the item [Memo].

(7) Make sure that the information for the U-WAVE-TCB/U-WAVE-TMB has shown up in the row of the number that you wish to set it to, and then press the “DATA” button (orange button) on the connection unit.

A successful connection will be indicated with the appearance of the mark “ $\checkmark$ ” in the [Connection] box.




### Tips:

- When the connection fails, press the “DATA” button again. There will be cases where the U-WAVE-TCB/U-WAVE-TMB cannot be detected depending on the timing you press the button.

(8) Press the “DATA” button on the connection unit again, and check if a measurement value can be transmitted.

If the value is displayed at the bottom-left of the window correctly, the setting up has been completed.




### Tips:

In the period immediately after setting up the U-WAVE-TCB/U-WAVE-TMB, there will be cases where measurement values cannot be transmitted even if the connection is successful. If such a case occurs, please send the measurement values again after a gap of a few seconds.

## 2.2. How to disconnect the U-WAVE-TCB/U-WAVE-TMB from the U-WAVEPAK-BW

When you wish to disconnect the U-WAVE-TCB/U-WAVE-TMB from this application, double-click on the mark “ $\checkmark$ ” in the appropriate box in the “Connection” column. In order to establish a connection again, press the “DARA” button on the connection unit.



### Tips:


If the mark “ $\checkmark$ ” in the “Connection” column does not disappear even a few seconds after double-clicking it, please double-click it again.

### Note:

- With the U-WAVE-TCB/U-WAVE-TMB connected via Bluetooth, the battery power will be consumed even if you are not using it. In the case that you will not use it for a long time, please store it with the Bluetooth connection disconnected.
- Measurement data is not sent when communication is reconnected. When you are reconnected, you confirm that measurement data is input into a terminal by all means, and please use it.

### 3. Inputting measurement values

- (1) In order to transfer measurement values received from the U-WAVE-TCB/U-WAVE-TMB to an Excel spreadsheet and the like, put the mark “✓” in the “Data I/F (Direct input) enable” box.
- (2) Measurement values received from the U-WAVE-TCB/U-WAVE-TMB can be transferred to an Excel spreadsheet and the like, only when the corresponding “Data out” box has been checked.



- (3) When you wish to input measurement values in an Excel spreadsheet, activate cells in the spread sheet, and then send the measurement values from the U-WAVE-TCB/U-WAVE-TMB with the keyboard input mode enabled.

Tips:

- “Data I/F (Direct input) enable” and “Data out” is enabled in the initial settings.
- Received measurement values can be transferred to an Excel spreadsheet only with the keyboard input mode enabled.
- If the measurement mode is set to [button-driven], measurement values can be sent by pressing the [DATA] button of the connection unit.
- If the measurement mode is set to [event-driven], this application outputs a measurement value in response to a data request from higher-level application software.

#### **4. Measurement modes**

-In the case of the [button-driven] mode,

If you press the [DATA] button on the connection unit once, the U-WAVE-TCB/U-WAVE-TMB will then send a measurement value once.

-In the case of the [event-driven] mode,

The U-WAVE-TCB/U-WAVE-TMB automatically sends a measurement value every 0.5 seconds, when the measurement value of the measurement tool (connected to the U-WAVE-TCB/U-WAVE-TMB) changes.

This application keeps the latest received measurement value and sends the latest measurement value in response to a request from higher-level application software and the like.

#### **Tips:**


In the [event-driven] mode, the battery power drains faster than in the [button-driven] mode because more frequent communication occurs.

## **5. Editing the settings**

### **5.1. Modifying the settings**

If you wish to change the settings information of a U-WAVE-TCB/U-WAVE-TMB set up in this application, please follow the procedure below.

- (1) Double-click on the corresponding number for the information to which you wish to make changes in the table [U-WAVE Information] or select the number from the drop-down list at the top-right of the window. Then click on the [U-WAVE Setting] button.



**U-WAVEPAK-BW ver.1.0.0**

**Mitutoyo**

**U-WAVEPAK-BW**

No. 1

**U-WAVE Information**


No.	Device ID	Device name	Measurement mode	Connection status	Data output
1	0600000019	0600000019	Button driven	✓	✓
2	0700000022	0700000022	Button driven	✓	✓
3	-	-	-	-	<input type="checkbox"/>
4	-	-	-	-	<input type="checkbox"/>
5	-	-	-	-	<input type="checkbox"/>
6	-	-	-	-	<input type="checkbox"/>
7	-	-	-	-	<input type="checkbox"/>

Data I/F (Direct input) enable

Group ID: 00 Band ID: 11

COM port number: COM3

0600000019 32.14mm

**U-WAVE Setting**

**Detected U-WAVE**

No. 1

Device ID : 0600000019


Device name :

Measurement mode :  Button driven  
 Event driven

Memo :

(2) Change the settings information.

When having finished the change, click on the [Decision] button.




Items to be changed	Contents
Device name	Change the device name.
Measurement mode	Select either the [button-driven] mode or the [event-driven] mode.
Memo	Change the contents written here
Delete information	Delete the information of the selected U-WAVE-TCB/U-WAVE-TMB

#### Tips:

There are cases where units of U-WAVE-TCB/U-WAVE-TMB which are not currently registered can be detected during the changing of information.

(3) Confirm that the changed settings information is successfully reflected in the [U-WAVE Information] window.



#### Tips:

-If you have changed the measurement mode, please follow the instructions below:

From the [button-driven] mode to the [event-driven] mode: Change the measurement value in the measuring tool connected to the U-WAVE-TCB/U-WAVE-TMB.


From the [event-driven] mode to the [button-driven] mode: Press the [DATA] button on the connection unit of the U-WAVE-TCB/U-WAVE-TMB.

## 5.2. Deleting the settings


If you wish to delete the settings information of the U-WAVE-TCB/U-WAVE-TMB set up in this application, follow the procedure below.

-Delete the settings information from the [U-WAVE Information] window

(1) Double-click on the corresponding number for the information you wish to delete in the table [U-WAVE Information] or select the number from the drop-down list at the top-right of the window. Then click on the [Delete Information] button




- (2) After the dialog [Delete of registration information] has shown up, click on the [OK] button to delete the settings information.




-Delete the settings information from the [U-WAVE Setting] window


(1) Double-click on the corresponding number for the information you wish to delete in the table [U-WAVE Information] or select the number from the drop-down list at the top-right of the window. Then click on the [U-WAVE Setting] button



(2) Click on the [Delete Information] button in the [U-WAVE Setting] window.



(3) After the dialog [Delete of registration information] has shown up, click on the [OK] button to delete the settings information.



## **6. Setting the connection to a higher-level application software (MeasurLink, ITPAK, etc.)**

To use this application with higher-level application software, please change the following numbers and IDs to be the same between this application and the higher-level application software.


Port number: Match the Port number of the higher-level application software to [COM port number] displayed at the bottom-left of this application's window.

Channel ID: Match the Channel ID of the higher-level application software to the number equal to the number in the table [U-WAVE Information] minus 1.

\*Example: In the case that the number in the table [U-WAVE Information] is 1, the channel number will be 00 (Channel ID = 00)

Group ID: Change the Group ID displayed at the bottom-right of the window of this application to the same value as that of the higher-level application software.


Band ID: Change the Band ID displayed at the bottom-right of the window of this application to the same value as that of the higher-level application software.




## 7. How to uninstall U-WAVEPAK-BW

If you wish to uninstall the U-WAVEPAK-BW set up in this PC, follow the procedure below.

- ① Please select this 『Windows Settings』⇒『Apps』.




- ② Please uninstall 『U-WAVEPAK-BW』 in the 『Apps & features』.




③ Click on the windows mark at the bottom left of the screen.

Select the 『Device Manager』 in the item.



④ Right-click 『Mitutoyo U-WAVE Virtual COM Port』 in the 『Ports(COM & LPT)』.

Select the 『Uninstall device』 and delete it.



# SERVICE NETWORK

As of Jan 2019

## Europe

### Mitutoyo Europe GmbH

Borsigstrasse 8-10, 41469 Neuss, GERMANY  
TEL: 49(0)2137 102-0 FAX: 49(0)2137 102-351

### Mitutoyo CTL Germany GmbH

Von-Gunzert-Strasse 17, 78727 Oberndorf, GERMANY  
TEL: 49(0)7423 8776-0 FAX: 49(0)7423 8776-99

### KOMEG Industrielle Messtechnik GmbH

Zum Wasserwerk 3, 66333 Völklingen, GERMANY  
TEL: 49(0)6898 91110 FAX: 49(0)6898 9111100

## Germany

### Mitutoyo Deutschland GmbH

Borsigstrasse 8-10, 41469 Neuss, GERMANY  
TEL: 49(0)2137 102-0 FAX: 49(0)2137 86 85

### M3 Solution Center Hamburg

Tempowerkring 9 im HIT-Technologiepark 21079 Hamburg,  
GERMANY  
TEL: 49(0)40 791894-0 FAX: 49(0)40 791894-50

### M3 Solution Center Berlin

Carl-Scheele-Straße 16, 12489 Berlin, GERMANY  
TEL: 49(0)30 2611 267

### M3 Solution Center Eisenach

Heinrich-Ehrhardt-Platz 1, 99817 Eisenach, GERMANY  
TEL: 49(0)3691 88909-0 FAX: 49(0)3691 88909-9

### M3 Solution Center Ingolstadt

Marie-Curie-Strasse 1a, 85055 Ingolstadt, GERMANY  
TEL: 49(0)841 954920 FAX: 49(0)841 9549250

### M3 Solution Center Leonberg

Steinbeisstrasse 2, 71229 Leonberg, GERMANY  
TEL: 49(0)7152 6080-0 FAX: 49(0)7152 608060

### Mitutoyo-Messgeräte Leonberg GmbH

Heidenheimer Strasse 14, 71229 Leonberg, GERMANY  
TEL: 49(0)7152 9237-0 FAX: 49(0)7152 9237-29

## U.K.

### Mitutoyo (UK) Ltd.

Joule Road, West Point Business Park, Andover, Hampshire  
SP10 3UX, UNITED KINGDOM  
TEL: 44(0)1264 353 123 FAX: 44(0)1264 354883

### M3 Solution Center Coventry

Unit6, Banner Park, Wickmans Drive, Coventry,  
Warwickshire CV4 9XA, UNITED KINGDOM  
TEL: 44(0)2476 426300 FAX: 44(0)2476 426339

### M3 Solution Center Halifax

Lowfields Business Park, Navigation Close, Elland, West  
Yorkshire HX5 9HB, UNITED KINGDOM  
TEL: 44(0)1422 375566 FAX: 44(0)1422 328025

### M3 Solution Center East Kilbride

The Baird Building, Rankine Avenue, Scottish Enterprise  
Technology Park, East Killbride G75 0QF, UNITED  
KINGDOM  
TEL: 44(0)1355 581170 FAX: 44(0)1355 581171

## France

### Mitutoyo France

Paris Nord 2-123 rue de la Belle Etoile, BP 59267 ROISSY EN  
FRANCE 95957 ROISSY CDG CEDEX, FRANCE  
TEL: 33(0)149 38 35 00

### M3 Solution Center LYON

Parc Mail 523, cours du 3ème millénaire, 69791 Saint-Priest,  
FRANCE  
TEL: 33(0)149 38 35 70

### M3 Solution Center STRASBOURG

Parc de la porte Sud, Rue du pont du péage, 67118  
Geispolsheim, FRANCE  
TEL: 33(0)149 38 35 80

### M3 Solution Center CLUSES

Espace Scionzier 480 Avenue des Lacs, 74950 Scionzier,  
FRANCE  
TEL: 33(0)1 49 38 35 90

### M3 Solution Center TOULOUSE

Aeroparc Saint Martin Cellule B08  
ZAC de Saint Martin du Touch 12 rue de Caulet  
31300 Toulouse, FRANCE  
TEL: 33(0)1 49 38 42 90

### M3 Solution Center RENNES

ZAC Mivoie  
Le Vallon  
35230 Noyal-Châtillon sur Seiche, FRANCE  
TEL: 33(0)1 49 38 42 10

## Italy

### MITUTOYO ITALIANA S.r.l.

CORSO EUROPA, 7 - 20020 LAINATE (MI), ITALY  
TEL: 39 02 935781 FAX: 39 02 9373290 • 93578255

### M3 Solution Center BOLOGNA

VIA DEI CARPINI 1/A - 40011 ANZOLA EMILIA (BO), ITALY  
TEL: 39 02 93578215 FAX: 39 02 93578255

### M3 Solution Center CHIETI

Contrada Santa Calcagna - 66020 Rocca S. Giovanni (CH),  
ITALY  
TEL: 39 02 93578280 FAX: 39 02 93578255

### M3 Solution Center PADOVA

VIA G. GALILEI 21/F - 35035 MESTRINO (PD), ITALY  
TEL: 39 02 93578268 FAX: 39 02 93578255

## Belgium / Netherlands

### Mitutoyo BeNeLux

### Mitutoyo Belgium N.V.

Hogenakkerhoekstraat 8, 9150 Kruibeke, BELGIUM  
TEL: 32(0)3-2540444 FAX: 32 (0)3-2540445

### Mitutoyo Nederland B.V.

Wiltonstraat 25, 3905 KW Veenendaal,

# SERVICE NETWORK

As of Jan 2019

THE NETHERLANDS  
TEL: 31(0)318-534911

## Sweden

**Mitutoyo Scandinavia AB**  
Släntvägen 6, 194 61 Upplands Väsby, SWEDEN  
TEL: 46(0)8 594 109 50 FAX: 46(0)8 590 924 10  
**M3 Solution Center Alingsås**  
Ängsvaktaregatan 3A, 441 38 Alingsås, SWEDEN  
TEL: 46(0)8 594 109 50 FAX: 46(0)322 63 31 62  
**M3 Solution Center Värnamo**  
Storgatsbacken 1, 331 30 Värnamo, SWEDEN  
TEL: 46(0)8 594 109 50 FAX: 46(0)370 463 34

## Switzerland

**Mitutoyo (Schweiz) AG**  
Steinackerstrasse 35, 8902 Urdorf, SWITZERLAND  
TEL: 41(0)447361150 FAX: 41(0)447361151  
**Mitutoyo (Suisse) SA**  
Rue Galilée 4, 1400 Yverdon-les Bains, SWITZERLAND  
TEL: 41(0)244259422 FAX: 41(0)447361151

## Poland

**Mitutoyo Polska Sp.z o.o.**  
Ul.Graniczna 8A, 54-610 Wrocław, POLAND  
TEL: 48(0)71354 83 50 FAX: 48(0)71354 83 55

## Czech Republic

**Mitutoyo Česko s.r.o.**  
Dubská 1626, 415 01 Teplice, CZECH REPUBLIC  
TEL: 420 417-514-011 FAX: 420 417-579-867  
**Mitutoyo Česko s.r.o. M3 Solution Center Ivančice**  
Ke Karlovu 62/10, 664 91 Ivančice, CZECH REPUBLIC  
TEL: 420 417-514-011 FAX: 420 417-579-867  
**Mitutoyo Česko s.r.o. M3 Solution Center Ostrava Mošnov**  
Mošnov 314, 742 51 Mošnov, CZECH REPUBLIC  
TEL: 420 417-514-050 FAX: 420 417-579-867  
**Mitutoyo Česko s.r.o. Slovakia Branch**  
Hviezdoslavova 124, 017 01 Povážská Bystrica, SLOVAKIA  
TEL: 421 948-595-590

## Hungary

**Mitutoyo Hungária Kft.**  
Záhony utca 7, D-épület / fsz, 1031 Budapest, HUNGARY  
TEL: 36(0)1 2141447 FAX: 36(0)1 2141448

## Romania

**Mitutoyo Romania SRL**  
1A Drumul Garii Odai Street, showroom, Ground Floor,  
075100 OTOPENI-ILFOV, ROMANIA  
TEL: 40(0)311012088 FAX: 40(0)311012089  
**Showroom in Brasov**

Strada Ionescu Crum Nr.1, Brasov Business Park Turnul 1,  
Mezanin, 500446 Brasov-Judetul Brasov, ROMANIA  
TEL/FAX: 40(0)371020017

## Russian Federation

**Mitutoyo RUS LLC**  
13 Sharikopodshipnikovskaya, bld.2, 115088 Moscow,  
RUSSIAN FEDERATION  
TEL: 7 495 7450 752

## Finland

**Mitutoyo Scandinavia AB Finnish Branch**  
Viherkiitäjä 2A, 33960, Pirkkala, FINLAND  
TEL: 358(0)40 355 8498

## Austria

**Mitutoyo Austria GmbH**  
Johann Roithner Straße 131 A-4050 Traun, AUSTRIA  
TEL: 43(0)7229 23850 FAX: 43(0)7229 23850-90  
**Götzis Regional Showroom**  
Lasten Straße 48A 6840, AUSTRIA

## Singapore

**Mitutoyo Asia Pacific Pte. Ltd.**  
**Head office / M3 Solution Center**  
24 Kallang Avenue, Mitutoyo Building, SINGAPORE 339415  
TEL: (65)62942211 FAX: (65)62996666

## Malaysia

**Mitutoyo (Malaysia) Sdn. Bhd.**  
**Kuala Lumpur Head Office / M3 Solution Center**  
Mah Sing Integrated Industrial Park, 4, Jalan Utarid U5/14,  
Section U5, 40150 Shah Alam, Selangor, MALAYSIA  
TEL: (60)3-78459318 FAX: (60)3-78459346  
**Penang Branch office / M3 Solution Center**  
No.30, Persiaran Mahsuri 1/2, Sunway Tunas, 11900 Bayan  
Lepas, Penang, MALAYSIA  
TEL: (60)4-6411998 FAX: (60)4-6412998  
**Johor Branch office / M3 Solution Center**  
No. 70, Jalan Molek 1/28, Taman Molek, 81100 Johor Bahru,  
Johor, MALAYSIA  
TEL: (60)7-3521626 FAX: (60)7-3521628

## Thailand

**Mitutoyo(Thailand)Co., Ltd.**  
**Bangkok Head Office / M3 Solution Center**  
76/3-5, Chaengwattana Road, Kwaeng Anusaowaree, Khet  
Bangkaen, Bangkok 10220, THAILAND  
TEL: (66)2-080-3500 FAX: (66)2-521-6136

## Chonburi Branch / M3 Solution Center

7/1, Moo 3, Tambon Bowin, Amphur Sriracha, Chonburi  
20230, THAILAND

# SERVICE NETWORK

As of Jan 2019

TEL: (66)2-080-3563 FAX: (66)3-834-5788

## **Amata Nakorn Branch / M3 Solution Center**

700/199, Moo 1, Tambon Bankao, Amphur Phanthong,  
Chonburi 20160, THAILAND

TEL: (66)2-080-3565 FAX: (66)3-846-8978

## **Indonesia**

### **PT. Mitutoyo Indonesia**

#### **Head Office / M3 Solution Center**

Jalan Sriwijaya No.26 Desa cibatu Kec. Cikarang Selatan Kab.  
Bekasi 17530, INDONESIA

TEL: (62)21-2962 8600 FAX: (62)21-2962 8604

## **Vietnam**

### **Mitutoyo Vietnam Co., Ltd**

#### **Hanoi Head Office / M3 Solution Center**

No. 07-TT4, My Dinh - Me Tri Urban Zone, My Dinh 1 Ward,  
Nam Tu Liem District, Hanoi, VIETNAM

TEL: (84)24-3768-8963 FAX: (84)24-3768-8960

#### **Ho Chi Minh City Branch Office / M3 Solution Center**

123 Dien Bien Phu Street, Ward 15, Binh Thanh District,  
Ho Chi Minh City, VIETNAM

TEL: (84)28-3840-3489 FAX: (84)28-3840-3498

## **Mitutoyo Philippines, Inc.**

### **Head Office/ M3 Solution Center**

Unit 2103, Bldg 2 GMV Building 2, 107 North Main Avenue,  
Laguna Technopark, Binan, Laguna 4024, Philippines  
TEL: (63)49 544 0272 FAX: (63)49 544 0272

## **India**

### **Mitutoyo South Asia Pvt. Ltd.**

#### **Head Office / M3 Solution Center**

C-122, Okhla Industrial Area, Phase-I, New Delhi-110 020,  
INDIA

TEL: 91(11)2637-2090 FAX: 91(11)2637-2636

#### **MSA Gurgaon technical center**

Plot No. 65, Phase-IV, Udyog Vihar, Gurgaon – 122016  
TEL: 91(0124) – 2340294

#### **Mumbai Region Head office**

303, Sentinel Hiranandani Business Park Powai,  
Mumbai-400 076, INDIA

TEL: 91(22)2570-0684, 837, 839 FAX: 91(22)2570-0685

#### **Pune Office / M3 Solution Center**

G2/G3, Pride Kumar Senate, F.P. No. 402 Off. Senapati Bapat  
Road, Pune-411 016, INDIA

TEL: 91(20)6603-3643, 45, 46 FAX: 91(20)6603-3644

#### **Bengaluru Region Head office / M3 Solution Center**

No. 5, 100 Ft. Road, 17th Main, Koramangala, 4th Block,  
Bengaluru-560 034, INDIA

TEL: 91(80)2563-0946, 47, 48 FAX: 91(80)2563-0949

#### **Chennai Office / M3 Solution Center**

No. 624, Anna Salai Teynampet, Chennai-600 018, INDIA

TEL: 91(44)2432-8823, 24, 27, 28 FAX: 91(44)2432-8825

## **Kolkata Office**

Unit No. 1208, Om Tower, 32, J.L.. Nehru Road, Kolkata-700  
071, INDIA

TEL: 91 33-22267088/40060635 FAX: (91)33-22266817

## **Ahmedabad Office/M3 Solution Center (Ahmedabad)**

A-104 & A-105, First Floor, Solitaire Corporate Park, Near  
Divya Bhaskar Press, S.G. Road, Ahmedabad - 380 015,  
INDIA

TEL: (91)079 - 29704902/903

## **Coimbatore Office (Coimbatore)**

Regus, Srivari Srimath, 3rd Floor, Door No: 1045, Avinashi  
Road, Coimbatore - 641 018, INDIA

TEL: (91)9345005663

## **Taiwan**

### **Mitutoyo Taiwan Co., Ltd. / M3 Solution Center Taipei**

4F., No.71, Zhouzi St., Neihu Dist., Taipei City 114, TAIWAN  
(R.O.C.)

TEL: 886(2)5573-5900 FAX: 886(2)8752-3267

### **Taichung Branch / M3 Solution Center Taichung**

1F., No.758, Zhongming S. Rd., South Dist., Taichung City 402,  
TAIWAN(R.O.C.)

TEL: 886(4)2262-9188 FAX: 886(4)2262-9166

### **Kaohsiung Branch / M3 Solution Center Kaohsiung**

1F., No.31-1, Haibian Rd., Lingya Dist., Kaohsiung City 802,  
TAIWAN (R.O.C.)

TEL: 886(7)334-6168 FAX: 886(7)334-6160

## **South Korea**

### **Mitutoyo Korea Corporation**

#### **Head Office / M3 Solution Center**

(Sanbon-Dong, Geumjeong High View Build.), 6F, 153-8,  
Ls-Ro, Gunpo-Si, Gyeonggi-Do, 15808 KOREA

TEL: 82(31)361-4200 FAX: 82(31)361-4202

#### **Busan Office / M3 Solution Center**

(3150-3, Daejeo 2-dong) 8, Yutongdanji 1-ro 49beon-gil,  
Gangseo-gu, Busan, 46721 KOREA

TEL: 82(51)718-2140 FAX: 82(51)324-0104

#### **Daegu Office / M3 Solution Center**

(Galsan-dong, Daegu Business Center), 301-Ho, 217,  
Seongseogongdan-ro, Dalseo-gu, Daegu 42704 KOREA

TEL: 82(53)593-5602 FAX: 82(53)593-5603

## **China**

### **Mitutoyo Measuring Instruments (Shanghai) Co., Ltd.**

12F, Nextage Business Center, No.1111 Pudong South Road,  
Pudong New District , Shanghai 200120, CHINA

TEL: 86(21)5836-0718 FAX: 86(21)5836-0717

### **Suzhou Office / M3 Solution Center (Suzhou)**

No. 46 Baiyu Road, Suzhou 215021, CHINA

TEL: 86(512)6522-1790 FAX: 86(512)6251-3420

# SERVICE NETWORK

As of Jan 2019

## **Wuhan Office**

Room 1701, Wuhan Wanda Center, No. 96, Linjiang Road,  
Wuchang District, Wuhan Hubei 430060, CHINA  
TEL: 86(27)8544-8631 FAX: 86(27)8544-6227

## **Chengdu Office**

1-701, New Angle Plaza, 668# Jindong Road, Jinjiang District,  
Chengdu, Sichuan 610066, CHINA  
TEL: 86(28)8671-8936 FAX: 86(28)8671-9086

## **Hangzhou Office**

Room 804, Eastern International Business Center Building 1,  
No.600 Jinsha Road  
Hangzhou Economic and Technological Development Zone,  
310018, CHINA  
TEL: 86(571)8288-0319 FAX: 86(571)8288-0320

## **Tianjin Office / M3 Solution Center Tianjin**

Room D 12/F, TEDA Building, No.256 Jie-fang Nan Road  
Hexi District,Tianjin 300042, CHINA  
TEL: 86(22)5888-1700 FAX: 86(22)5888-1701

## **Changchun Office**

Room 815, 8F, Building A1, Upper East International  
No.3000 Dongsheng Street, Erdao District, Changchun, Jilin,  
130031, CHINA  
TEL: 86(431)8192-6998 FAX: 86(431)8192-6998

## **Chongqing Office**

Room 1312, Building 3, Zhongyu Plaza, No.86, Hongjin  
Avenue, Longxi Street, Yubei District, Chongqing, 400000,  
CHINA  
TEL: 86(23)6595-9950 FAX: 86(23)6595-9950

## **Qingdao Office**

Room 638, 6F, No.192 Zhengyang Road, Chengyang District,  
Qingdao, Shandong, 266109, CHINA  
TEL: 86(532)8096-1936 FAX: 86(532)8096-1937

## **Xi'an Office**

Room 805, Xi'an International Trade Center, No. 196  
Xiaozhai East Road, Xi'an, 710061, CHINA  
TEL: 86(29)8538-1380 FAX: 86(29)8538-1381

## **Dalian Office / M3 Solution Center Dalian**

Room 1008, Grand Central IFC, No.128 Jin ma Road,  
Economic Development Zone, Dalian 116600, CHINA  
TEL: 86(411)8718 1212 FAX: 86(411)8754-7587

## **Zhengzhou Office**

Room1801,18/F,Unit1,Building No.23, Shangwu Inner Ring  
Road, Zhengdong New District,Zhengzhou City, Henan  
Province, 450018,CHINA  
TEL: 86(371)6097-6436 FAX: 86(371)6097-6981

## **Mitutoyo Leepot Metrology (Hong Kong) Limited**

Room 818, 8/F, Vanta Industrial Centre, No.21-33, Tai Lin Pai  
Road, Kwai Chung, NT, Hong Kong  
TEL: 86(852)2992-2088 FAX: 86(852)2670-2488

## **Mitutoyo Leepot Metrology (Dongguan) Limited /**

**M3 Solution Center Dongguan**  
No.26, Guan Chang Road, Chong Tou Zone, Chang An Town,

## **Dong Guan, 523855 CHINA**

TEL: 86(769)8541 7715 FAX: 86(769)-8541 7745

## **Mitutoyo Leepot Metrology (Dongguan) Limited – Fuzhou office**

Room 2104, City Commercial Centre, No.129 Wu Yi Road N.,  
Fuzhou City, Fujian Province, CHINA  
TEL: 86 591 8761 8095 FAX: 86 591 8761 8096

## **Mitutoyo Leepot Metrology (Dongguan) Limited – Changsha office**

Room 2207, Shiner International Plaza, No. 88, Kaiyuan  
Middle Road, Changsha City, Hunan, China  
TEL: 86 731 8401 9276 FAX: 86 731 8401 9376

## **Mitutoyo Measuring Instruments (Suzhou) Co., Ltd.**

No. 46 Baiyu Road, Suzhou 215021, CHINA  
TEL: 86(512)6252-2660 FAX: 86(512)6252-2580

## **U.S.A.**

### **Mitutoyo America Corporation**

965 Corporate Boulevard, Aurora, IL 60502, U.S.A.  
TEL: 1-(630)820-9666 Toll Free No. 1-(888)648-8869  
FAX: 1-(630)978-3501

### **M3 Solution Center-Illinois**

965 Corporate Boulevard, Aurora, IL 60502, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(630)978-3501

### **M3 Solution Center-Ohio**

6220 Hi-Tek Court, Mason, OH 45040, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(513)754-0718

### **M3 Solution Center-Michigan**

46850 Magellan Drive, Suite 100, Novi, MI 48377, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(248)926-0928

### **M3 Solution Center-California**

16925 E. Gale Avenue, City of Industry, CA 91745, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(626)369-3352

### **M3 Solution Center-North Carolina**

11515 Vanstory Drive, Suite 140, Huntersville, NC 28078, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(704)875-9273

### **M3 Solution Center-Alabama**

2100 Riverchase Center, Suite 106, Hoover, AL 35244, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(205)988-3423

### **M3 Solution Center-Washington**

1000 SW 34th Street Suite G, Renton, WA 98057 U.S.A.  
TEL: 1-(888)648-8869

### **M3 Solution Center-Texas**

4560 Kendrick Plaza Drive, Suite 120, Houston, TX 77032,  
U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(281)227-0937

### **M3 Solution Center-Massachusetts**

753 Forest Street, Suite 110, Marlborough,MA 01752, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(508)485-0782

### **Mitutoyo America Corporation Calibration Lab**

965 Corporate Boulevard, Aurora, IL 60502, U.S.A.  
TEL: 1-(888)648-8869 FAX: 1-(630)978-6477

# SERVICE NETWORK

As of Jan 2019

## **Micro Encoder, Inc.**

11533 NE 118th Street, Kirkland, WA 98034-7111, U.S.A.  
TEL: 1-(425)821-3906 FAX: 1-(425)821-3228

## **Micro Encoder Los Angeles, Inc.**

16925 E. Gale Avenue, City of Industry, CA 91745-1806 U.S.A.  
TEL: 1-626-961-9661 FAX: 1-626-333-8019

## **Canada**

### **Mitutoyo Canada Inc.**

2121 Meadowvale Blvd., Mississauga, Ont. L5N 5N1.,  
CANADA  
TEL: 1-(905)821-1261 FAX: 1-(905)821-4968

### **Montreal Office**

7075 Place Robert-Joncas Suite 129, Montreal, Quebec H4M  
2Z2, CANADA  
TEL: 1-(514)337-5994 FAX: 1-(514)337-4498

## **Brazil**

### **Mitutoyo Sul Americana Ltda.**

**Head office / M3 Solution Center / Factory**  
Rodovia Índio Tibiriça 1555, Bairro Raffo, CEP 08655-000  
Suzano – SP, Brasil  
TEL: 55(11) 5643- 0040

## **Argentina**

### **Mitutoyo Sul Americana Ltda.**

**Argentina Branch / M3 Solution Center**  
Av. B. Mitre 891/899 – C.P. (B1603CQI) Vicente López –Pcia.  
Buenos Aires – Argentina  
TEL: 54(11)4730-1433 FAX: 54(11)4730-1411

### **Sucursal Cordoba / M3 Solution Center**

Av. Amadeo Sabattini, 1296, esq. Madrid Bº Crisol Sur – CP  
5000, Cordoba, ARGENTINA  
TEL/FAX: 54(351)456-6251

## **Mexico**

### **Mitutoyo Mexicana, S.A. de C.V.**

Prolongación Industria Eléctrica No. 15 Parque Industrial  
Naucalpan  
Naucalpan de Juárez, Estado de México C.P. 53370, MÉXICO  
TEL: 52(01-55)5312-5612

### **Monterrey Office/ M3 Solution Center Monterrey**

Blv. Interamericana No. 103, Parque Industrial FINSA,  
C.P. 66636 Apodaca, N.L., MÉXICO  
TEL: 52(01-81) 8398-8227/8228/8242/8244  
FAX: 52(01-81) 8398-8226

### **Tijuana Office/ M3 Solution Center Tijuana**

Calle José María Velazco 10501-C, Col. Cd. Industrial Nueva  
Tijuana, C.P. 22500 Tijuana, B.C., MÉXICO  
TEL: 52(01-664) 647-5024

### **Querétaro Office / M3 Solution Center Querétaro**

Av. Cerro Blanco No.500-1, Colonia Centro Sur, Querétaro,  
Querétaro, C.P. 76090, MÉXICO

TEL: 52(01-442)340-8018, 340-8019 and 340-8020

FAX: 52(01-442)340-8017

## **Mitutoyo Mexicana, S.A. de C.V. Querétaro Calibration Laboratory**

Av. Cerro Blanco 500 30 Centro Sur, Querétaro, Querétaro,  
C.P. 76090, MÉXICO  
TEL: 52(01-442)340-8018, 340-8019 and 340-8020  
FAX: 52(01-442)340-8017

### **Aguascalientes Office / M3 Solution Center**

Av. Aguascalientes No. 622, Local 15 Centro Comercial El  
Cilindro Fracc. Pulgas Pandas Norte, C.P. 20138,  
Aguascalientes, Ags. MÉXICO  
TEL: 52(01-449)174-4140 and 174-4143

### **Irapuato Office / M3 Solution Center**

Boulevard a Villas de Irapuato No. 1460 L.1 Col. Ejido  
Irapuato C.P. 36643  
Irapuato, Gto., MÉXICO  
TEL: 52(01-462)144-1200 and 144-1400